



## Adobe Illustrator – Lesson 16 Working with Gradients Transparency Menu

### Cell Phone

1. START>PROGRAMS>ADOBE ILLUSTRATOR CS3
2. File>New and use these settings. Be sure to change Units to Inches if necessary.



3. Create a 4"x7" rounded rectangle by selecting your Rounded Rectangle Tool. Click anywhere on your canvas to open the dialogue box. Enter these settings:




You should have this:



4. Select the Rounded Rectangle. Change your Stroke color to 70% black.



5. Change the Fill color to 30% black.




You should have something like this:



6. Select the rounded rectangle. Go to Edit>Copy, Edit>Paste to make a copy.




7. With the copy selected, go to Object>Transform>Scale and enter 98% as shown:



8. Place the smaller rounded rectangle on top as shown:



9. Select your Black Arrow Selection Tool. Drag a selection box around both rectangles to select them at the same time. Go to Window>Align. Click the Horizontal Align Center and Vertical Align Center buttons to line up both shapes evenly:



10. Select the smaller rounded rectangle. Go to Window>Swatches>Gradients>Metals (Note: Gradients are a mix of two or more colors).




11. Select the white gold swatch.




12. You should have something like this:



13. Select the smaller rounded rectangle again. Go to Edit>Copy, Edit>Paste. Fill the copy with black and place it as shown:




14. Select the black rounded rectangle. Go to Object>Transform>Scale and enter 96% as shown:




15. Select your Black Arrow Selection Tool. Drag a selection box around all three rectangles. Go to Window>Align. Click the Horizontal Align Center and Vertical Align Center buttons again to line up both shapes evenly:




16. Now that you have created the background of the cell phone, double-click Layer 1 and rename it Background:




17. Click the “Create New Layer” to make a new layer and rename it Screen:



18. Set your Fill and Stroke colors to white and black. Draw a rectangle as shown:





19. Select the white rectangle. On your Swatch menu, click the Linear Gradient 1 swatch to fill it with the gradient.




20. Select the rectangle. Your Gradient menu should be open for you. If not, just go to Window>Gradient.



21. On your Swatch menu, drag the following blue swatch directly onto the black color box on your gradient slider: C=80 M=5 Y=10 K=0



You should get this:




22. With the rectangle still selected, drag the following blue onto the left color box on your gradient slider: C=30 M=0 Y=10 K=0






23. Drag the left blue box to the right as shown to adjust the gradient. Or just type in 50 in the Location % box.



24. Draw a rectangle over the grey one. (If you want to save the new gradient swatch, go to your Swatch menu and click New Swatch.)



25. Add two small rectangles with a transparent fill and white stroke as shown:



26. Add a small green rectangle and then a red one and place them as shown:




27. Add a small rectangle with a transparent fill and white stroke. Then type the number 1 in white.



28. Click on the rectangle. Hold the ALT key and drag a copy to the right. Click anywhere on the artboard to deselect the rectangle. Then click the rectangle once again, hold ALT and drag so you have this:



29. Click on the first rectangle. Hold SHIFT and click the other two rectangles to select them all. Go to Window>Align and select the vertical Align Top button to line up the rectangles:



You should get this:



28. Repeat steps 25-27 and add the numbers and letters as shown below. Adjust the font size as needed to fit the numbers and letters.

29. Add a power button and then you are done!

